


Windows MAC Addresses

Goal: Find MAC Addresses in Microsoft Windows.


Here are some techniques for finding MAC addresses on Microsoft Windows using the Control Panel and the command line.




- 1. Find the MAC Address of the Windows PC. There are two methods you can use:
 - A. Method 1: use the Control Panel
 - A. Click Start, Run, control, [enter]




B. Search and select Network Status and Devices




c. We click on our device, Ethernet 3:




D. Click **Details...**



E. Details will show the MAC address (physical address):



- F. (Suggested) Set the IP address if you have not already. For more information see Finding Windows IP Address
- B. **Method 2:** use the DOS command-line. You want to correlate the IP address and MAC address of the Windows ethernet port:
 - A. Click Start, Run, and type cmd, and press [Enter]



B. Show interfaces by name with the command: netsh interface ipv4 show addresses

```
C:\Users\IEUser\netsh interface ipv4 show addresses

Configuration for interface "Ethernet 4"
DHCP enabled:
IP Address:
Subnet Prefix:
InterfaceMetric:

Configuration for interface "Ethernet 3"
DHCP enabled:
IP Address:
Subnet Prefix:
InterfaceMetric:

Configuration for interface "Ethernet 2"
DHCP enabled:
IP Address:
Subnet Prefix:
IP Address:
IP A
```

C. (Optional) if you do not see results, you might need to start the network autodiscovery service: net start dot3svc


```
$ net start dot3svc
The Wired AutoConfig service is starting.
The Wired AutoConfig service was started successfully.
```

D. (Optional) Depending on the edition of Windows, the command netsh lan show interfaces will display mac addresses.

```
netsh lan show interfaces
There are 4 interfaces on the system:
                                   : Ethernet 3
: Intel(R) PRO/1000 MT Network Connection #2
: a3ac1715-8740-4b8f-8022-fec68d9bbd6e
: 08-00-27-C4-4E-4F
      Name
      Description
      GUID
      Physical Address :
                                    : Connected. Network does not support authentication.
      State
                                   : Ethernet 2
: Intel(R) PRO/1000 MT Network Connection
: 6358aef5-ff9f-445c-81db-9bec6c0d477a
: 08-00-27-3A-3C-FB
      Description :
GUID :
Physical Address :
                                    : Connected. Network does not support authentication.
      Name : Ethernet
Description : Intel(R) PRO/1000 MT Desktop Adapter
GUID : f0c1f253-3499-4d73-88f5-1ff2687633d1
Physical Address : 08-00-27-12-89-E9
State : Connected. Network does not support authentication.
                                    : Ethernet 4
: Intel(R) PRO/1000 MT Network Connection #3
: 4ccf6f8e-c1ee-44af-b0ef-2dc36c1d8a07
: 08-00-27-AC-4C-4A
      Description
GUID
      Physical Address :
      State
                                       Connected. Network does not support authentication.
```


E. Show mac addresses with: getmac /v /fo csv

(The CSV formatted command of the command ensures that we will see the entire name of the interface which can be trimmed short in the default output format.)



F. These commands will make it easier to copy using **notepad**:

```
netsh interface ipv4 addresses > ifnotes.txt
getmac /v /fo csv >>ifnotes.txt
notepad ifnotes.txt
```



G. Now you can easily copy the values:

```
ifnotes - Notepad
File Edit Format View Help
Configuration for interface "Ethernet 4"
       DHCP enabled:
IP Address:
                                                                            Yes
169.254.3.216
                                                                            169.254.0.0/16 (mask 255.255.0.0)
       Subnet Prefix:
       InterfaceMetric:
Configuration for interface "Ethernet 3"
DHCP enabled:
IP Address:
                                                                            10.26.0.10
                                                                            10.26.0.0/24 (mask 255.255.255.0)
       Subnet Prefix:
       InterfaceMetric:
Configuration for interface "Ethernet 2"
DHCP enabled:
IP Address:
                                                                            Yes
192.168.100.135
       Subnet Prefix:
                                                                            192.168.100.0/24 (mask 255.255.255.0)
      Default Gateway:
Gateway Metric:
InterfaceMetric:
                                                                            192.168.100.1
Configuration for interface "Ethernet"
       DHCP enabled:
       IP Address:
Subnet Prefix:
Default Gateway:
                                                                            res
10.0.2.15
10.0.2.0/24 (mask 255.255.255.0)
10.0.2.2
       Gateway Metric:
       InterfaceMetric:
                                                                           10
Configuration for interface "Loopback Pseudo-Interface 1" DHCP enabled: No IP Address: 127.0.0.1
                                                                            127.0.0.0/8 (mask 255.0.0.0)
       Subnet Prefix:
       InterfaceMetric:
"Connection Name", "Network Adapter", "Physical Address", "Transport Name"

"Ethernet", "Intel(R) PRO/1000 MT Desktop Adapter", "08-00-27-12-89-E9", "\Device\Tcpip_{F0C1F253-3499-4D73-88F5-1FF2687633D1}"

"Ethernet 2", "Intel(R) PRO/1000 MT Network Connection", "08-00-27-3A-3C-FB", "\Device\Tcpip_{6358AFF5-FF97-445C-81D8-9BEG6G09477A}"

"Ethernet 3", "Intel(R) PRO/1000 MT Network Connection #2", "08-00-27-AC-4C-4A", "\Device\Tcpip_{43AC1715-8740-48BF-8022-FEG68D9BBD6E}"

"Ethernet 4", "Intel(R) PRO/1000 MT Network Connection #3", "08-00-27-AC-4C-4A", "\Device\Tcpip_{44CF6F8E-C1EE-44AF-B0EF-2DC36C1D8A07}"
```

www.candelatech.com | sales@candelatech.com | +1.360.380.1618